


20.6 Conductors and Electric Fields

Conductor \Rightarrow charges can move freely.




$\vec{E} = 0$ inside a conductor

Any excess charge lies on the surface


$\vec{E} \perp$ surface

$|\vec{E}| = \sigma / \epsilon_0$ adjacent to the surface ($\sigma = \text{charge density}$)

E & σ largest near points




Shielding / Faraday cage



20.7 Forces and Torques in Electric Fields


Forces: Use $\vec{F} = m\vec{a}$, where $\vec{F} = q\vec{E}$
for a charge q in an electric field \vec{E} .

Example: Use parallel plates to stop an electron: An electron has an initial speed of 3.00×10^6 m/s, what magnitude and direction of electric field would be needed to bring it to rest in 0.0500 m?



Charge one plate $+Q$ the other $-Q$.

Poll: what orientation of charges do we need?



$\vec{F} = q\vec{E}$. Since $q = -e$, $\vec{F} = -e\vec{E}$,
 so a field to the right creates a force to
 the left.

Use $F = ma$

$$qE = ma$$

$$(-e)E = ma$$

what a do you want?

$$v_f^2 = v_i^2 + 2ad$$

$$a = \frac{v_f^2 - v_i^2}{2d} = \frac{0 - v_i^2}{2d}$$

$$\therefore (-e)E = -\frac{mv_i^2}{2d}$$


$$E = \frac{mv_i^2}{2ed} = \frac{(9.11 \times 10^{-31} \text{ kg})(3.0 \times 10^6 \text{ m/s})^2}{2(1.602 \times 10^{-19} \text{ C})(0.01 \text{ m})}$$

$$E \approx 512 \text{ N/C}$$

0.05

(We will later see how to approach this
 problem using energy.)
 See Example 20.15.

Forces and Torques on a Dipole




Dipole moment $\vec{p} \equiv Q \cdot L$

e.g. HCl $\vec{p} \approx 3.4 \times 10^{-30} \text{ C} \cdot \text{m}$

A diagram showing a dipole with charges \oplus and \ominus and a dipole moment vector \vec{p} pointing upwards.

What happens to \vec{p} in an imposed uniform electric field \vec{E} ?



Net force = 0

But ... tends to rotate to align with \vec{E} .

Torque: $|\tau| = pE \sin \theta$

(no quantitative calculations).